Air Quality Data: A New Conceptual Approach



Spatial Data Analysis Workshop Alan J. Cimorelli, EPA Region 3 December 3, 2001

Outline

- Goal
- Present Concept
- New Concept
- Advantages
- Details of Approach
- Approach to Network Design
- Network Design Example
- Next Steps

Basic Goal: Air Quality Data Collection

Produce as complete and accurate a picture (spatial field) of air quality in as cost effective a manner as possible.

Present Concept

- Tenets:
 - Air Quality Data (AQD) are truth
 - If no monitors then no information
- Problems
 - Ignores substantial & relevant information (i.e., Interpolation)
 - Concept is too limited for planning purposes (we must estimate)
 - Therefore we use AQD to create an implicit spatial picture: For Designations AQD represent only the county in which they are taken
 - Disincentive to monitor

New Concept

- Tenets:
 - Measured or interpolated data are the same except for uncertainty – They are an estimate of the actual field
 - Define Air quality as an estimated field of concentrations with associated uncertainties
- Estimate Concentration Field:
 - Recognize that AQD are simply a sample of the "Actual" air quality FIELD
 - Then, estimate the complete field by interpolating (kriging) the AQD
- Estimate an associated uncertainty field based on area modeling


Advantages to New Concept

- A complete field of air quality is available for policy development, trends analysis, etc.
- Robust: Changes to an optimized network should not significantly affect the estimated field
- Removes monitoring disincentive
- Provides a direct blueprint for developing cost-effective networks


Constructing Concentration Fields

- Establish the best variogram model for the concentration field base on:
 - Air quality data
 - BENCHMARK concentration field from area modeling (modeling data must adequately characterize important features of the field)
- Estimate, through kriging, the actual concentration field using:
 - The optimized variogram model
 - All available monitored air quality values both within and outside the area

1999 8hr. Ozone Design Value: Kriged Grid (Linear Variogram) with Network Overlay




1999 8 hr. Ozone Design Values: Kriged Contour Map (Linear Variogram)




Constructing Uncertainty Fields


- Develop a subset of the benchmark (photochemical dispersion modeled) data based on network monitor locations only
- Estimate the full benchmark concentration field by kriging the benchmark data subset
- Compare the full benchmark field with the estimated field from the benchmark subset
- Construct a field of residuals (the uncertainty field)

BENCHMARK Data Set
4th High 8hr. Ozone: UAM-V Model Output
1996 Emissions Inventory
30 Days of 1995 Met




Constructing Data Subset (modeled values at monitor locations) from Benchmark UAM-V Modeling





Air Quality is defined as an interpolated concentration field plus an associated uncertainty field

1999 8hr. DV O₃



Network Design: Premise


The primary purpose of a monitoring network is to estimate a variety of pollutant fields with the lease uncertainty considering resource demands and other appropriate design criteria

Network Design: Approach

- Develop appropriate benchmark data sets (modeled)
 - Multiple episodes
 - Multiple metrics
 - Multiple pollutants
- Construct potential new network designs (i.e., data subsets from the benchmark field)
- Estimate (krig) concentration fields for each network design
- Develop decision criteria (e.g.):
 - Compare each estimated field to the benchmark fields using statistics such as: Correlation Coefficient; Maximum residual; etc.
 - Multiple areas
 - Resource demand
 - State preference
 - Community preference
 - Other needs: e.g., statutory, trends, PSI, etc.
- Use MIRA to choose design


Network Design: Example

- Consider 4 networks:
 - \blacksquare 1999 O_3 network
 - Reduced network (28 Rg III monitors removed): For counties having multiple monitors, remove all but the one having the max 1999 8 hr. design value
 - Network A: Add 1 monitor to Albemarle, VA
 - Network AH: Add a monitor each to Albemarle, VA & Harrison, WV
- Consider 3 areas:
 - Region 3
 - Region 3's Non-Attainment counties
 - Region 3's Attainment counties
- Consider 1 decision criteria: correlation coefficient



1999 O₃ Network (Corr Coeff = 0.89)


Reduced Network (Corr Coeff = 0.88)



1999 O₃ **Network** (Corr Coeff = 0.89) **Network A** (Corr Coeff = 0.90) coopera, nongood, songood, **SERVICE** PACHMICONH HATTON WHEN'T SERMI PEHOLETON CHARGER CAMPER RECEIPEDRA **ВЕТЕМИРИКА** SHATTON неприн OWNERS AND PERSONS HOUSE idea. LINES emakere 60000 tomas **CREDWINE** DOTETORS AMELIA 1.3 DISTRICTOR 1.2 POLICEON **Ratio of Kriged Network AH** To Benchmark **HARRIGHTHS** (Corr Coeff = 0.91)0.9 ECOCHERNO. ORDERS. 0.83


1999 O_3 Network 1 hr. Non-Attn. Areas (Corr Coeff = 0.97) Reduced Network
1 hr. Non-Attn. Areas
(Corr Coeff = 0.97)






1999 O₃ Network **1 hr. Attn. Areas** (Corr Coeff = 0.82)


Reduced Network 1 hr. Attn. Areas (Corr Coeff = 0.82)






1999 O_3 Network 1 hr. Attn. Areas (Corr Coeff = 0.82)

Network AH
1 hr. Attn. Areas
(Corr Coeff = 0.86)





Next Steps

- Optimized variogram model
- Proceed w/ network reassessment
 - Establish set of benchmark data sets:
 - Additional episodes
 - Additional metrics
 - Decide on comparison statistics
 - Establish other criteria
- Apply new concept to O_3 and $PM_{2.5}$ non-attainment designations i.e., for counties wo/ monitors use interpolated data.
- Convince DECISION MAKERS to change their view